**Note: This IBM PC BIOS API call is for DOS/Win16 personality only. Use Family API for portability.**

**Note: osFree Macro Library provides macros for most of functions**

2022/03/13 05:41 · prokushev · 0 Comments

# @WrtTTY

## Version

IBM 5150 and higher

## Brief

Write char in TTY mode

## BIOS Interrupt

INT10H: 0EH

## Family API

VioWrtTTY

## Syntax

```
@WrtTTY char, page
```

## Parameters

- char (BYTE) - character code
- page (BYTE) - optional video page number

# Return

none

| **IBM PC BIOS API** | |
|---|---|
| Video I/O | **INT 10H**: 00H, 01H, 02H, 03H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0CH, 0DH, 0EH, 0FH |
| Hardware info | INT 11H, INT 12H |
| Serial I/O | **INT 14H**: 00H, 01H, 02H, 03H |
| Tape I/O | **INT 15H**: 00H, 01H, 02H, 03H |
| Keyboard I/O | **INT 16H**: 00H, 01H, 02H |
| Printer I/O | **INT 17H**: 00H, 01H, 02H |
| Disk I/O | **INT 13H**: 00H, 01H, 02H, 03H, 04H, 05H |
| Date and Time | **INT 1AH**: 00H, 01H |
| **osFree Macro Library** | |
| Video I/O | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info | @Equipment @MemSize |
| Serial I/O | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus |
| Tape I/O | @TapeOn @TapeOff @TapeRead @TapeWrite |
| Keyboard I/O | @KbdStatus @CharIn @CharPeek |
| Printer I/O | @PrnPrint @PrnInit @PrnStatus |
| Disk I/O | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat |
| Date and Time | @SetTime @GetTime |
| Mouse | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion |
| Memory manager | @ModBlok SET_BLOCK |

2022/10/04 14:28 · prokushev · 0 Comments
2022/03/13 05:54 · prokushev · 0 Comments

From:
https://www.osfree.ru/doku/ - **osFree wiki**

Permanent link:
**https://www.osfree.ru/doku/doku.php?id=en:docs:macrolib:wrttty**

Last update: **2022/10/08 05:53**